

Sybase ProjectPAK Installation Instructions

1. Install the Sybase Database Server and Shared Database


1. Click the Download button. Once downloaded, open the Sybase ProjectPAK.zip file and double-click Setup.exe to begin installation. You'll be prompted for the password that was provided to you. Click Run, if prompted, and follow the instructions on the screen. We recommend keeping the installation defaults.
2. Start the new SQL Anywhere Server by selecting **Start | Programs | SQL Anywhere Server 17 | Server**. You should see the SQL Anywhere window display. Once it starts the database and the necessary networking communication protocols, it minimizes itself. You'll see its icon on the task bar. If the server doesn't start, or you receive an error message, call TradeSoft technical support. To shut down the TradeSoft server, right mouse click the server icon and select "Exit".

Note: You should leave the server running because subsequent steps depend on it being running.

Also, if you are running Windows 7/Server 2008 or higher, it is highly recommended that you start the installation program by right-clicking on it and choosing the Run As Administrator command.

2. Creating the Sybase Service

1. We highly recommend you create a service on your server that automatically starts the database when your server reboots. Click on Start | Programs | SQL Anywhere 17. Click on **Create Sybase Service**. You will see a command prompt screen appear, run a command then disappear.



```
C:\> Create Sybase Service (64-bit)
SQL Anywhere Service Utility Version 17.0.10.6089
Service "TradeSoft17" was created successfully.
The SQL Anywhere - TradeSoft17 service is starting.._
```

Note: If you did not keep the installation defaults, you will need to update the .bat file FIRST before running the service. Click on Start | Programs | SQL Anywhere 17. Right click on **Create Sybase Service** and click Edit. If you did not keep the installation defaults, you'll need to adjust the PpakSrvr17 directory. Click File | Save.

```
@echo off
rem *****
rem TradeSoft, Inc.
rem support@tradesoftinc.com
rem 770-579-1922
rem *****

cd C:\Program Files\SQL Anywhere 17\Bin64\
dbsvc -as -i -s automatic -t network -w TradeSoft17 "C:\Program Files\SQL Anywhere 17\Bin64\dbsrv17.exe" -x TCP/IP
-n TradeSoft17 "C:\PpakSrvr17\engine.db"
net start SQLANYs_TradeSoft17
exit
```